

APPLICATION


TEMPRID

Temprid can be safely applied to headboards, mattresses, box springs, nightstands and the interior of bed frames, including all cracks and joints. For infested mattresses, remove linens and wash before reuse. Apply Temprid to tufts, seams, folds, and edges until moist. Allow drying before remaking bed. **DO NOT** spray bed linens or other materials that come in direct contact with occupants/customers. Temprid may be reapplied every 7-10 days as needed.

THE ONLY PRODUCT YOU NEED FOR BED BUG CONTROL

CUMULATIVE MORTALITY AFTER 1 HOUR EXPOSURE

■ 2 HR ■ 7 DAY




OVERALL AVERAGES FOR BOTH STRAINS (SUSCEPTIBLE, RESISTANT) AND SUBSTRATES (HARDBOARD, COTTON TICKING)

TEMPO 1% DUST AND DRIONE DUST

These are ideal for application in the hard-to-reach areas where Temprid can't be applied. The combination of Temprid with either dust insecticide provides complete control of void infestations, limits bed bugs from spreading to other rooms, and ensures complete elimination of bed bugs. Tempo 1% and Drione can be applied to:

- Electrical outlets
- Harborages in voids
- Cracks and crevices
- Voids in bedframes and furniture
- Beneath carpet edges along the tack strips

DUST EFFICACY ON PYRETHROID RESISTANT BED BUG



SOURCE: ALVERO, ET. AL, UKY, 2010



PREVENTION AND MONITORING

Steps may be taken to prevent the spread of bed bugs and include:

- Educating customers that sanitation will NOT eliminate bed bugs
- Advising customers to have a clutter free environment before and after treatment
- Moving furniture from contact with walls and infested furniture
- Initial vacuum of mattresses, beds, harborages, etc. (removes bugs/debris)
- Treating harborages with properly labeled residual
- Dusting electrical boxes and voids
- Sealing harborages shut

BACKED by BAYER

Like all our products, Temprid is Backed by Bayer - a company dedicated to innovative solutions, support and protecting tomorrow today.

Learn more at BackedbyBayer.com/Temprid